



Assorted Features

2019 RiverWare User Group Meeting
David Neumann

Assorted Features

- 1. Physical Process Modeling
- 2. New Timestep Sizes
- 3. Slot Displays for Flow/Volumes
- 4. Plotting
- 5. Output Canvas
- 6. RPL Enhancements

Physical Process Modeling




New Aquifer Object





- Models deep saturated groundwater flow
- Connect in up to 6 directions (upstream, downstream, left, right, above, below)
- Solves at
 - Run Timestep or
 - Larger Timestep
- Larger spatial extent than GW objects

Aquifer Setup – Cross Section



Aquifer below Groundwater





Aquifer Equations

```
Flow LRUDB = Conductance LRUDB × (Head LRUDB Previous – Head Previous)

Flow Above Aggregated = aggregation of (Flow Above)

Storage(t) = Storage(t-1) + (Flow Upstream + Flow Downstream + Flow Left + Flow Right + Flow Above Aggregated + Flow Below – Pumped Flow + Specified Inflow) × \Delta t

Head (t) = Head (t-1) + \frac{Storage(t) - Storage(t-1)}{Storativity \times Area}
```

Aquifer / Groundwater **Timestep Interaction**

Aquifer Object



Groundwater Object




Date	Head	Day	Head Previous (ft)		Day	Deep Aquifer Elevation Previous		Elevation Previous	
Month 1	4321	30	4320		30	4320		4345	
		1	4321		1	4321		4345.1	
		2	4321		2	4321		4345.2	
		3	4321		3	4321		4345.2	
		4	4321		4	4321		4345.2	
		5	4321		5	4321		4345.2	
		6	4321		6	4321		4345.2	
		7	4321		7	4321		4345.2	
		30	4321		30	4321		4345.4	
Month 2	4322	31	4321		31	4321		4345.5	
	h.	1			1	4322		4345.5	

New Timestep Sizes

New Timestep Sizes


- 5 and 15 Minute
 Timesteps
- Modification to names of other timestep sizes for consistency
- Was: Hourly, Annual
- Now: 1 Hour, 1 Year



Slot Displays for Alt Units


Slot Displays for Alt Units

- Slot and Slot Viewer
- SCT
- Accounting Dialogs
- RiverWISE (7.6)




Plotting

Plotting - New Mouse Actions





- Scroll the mouse wheel to zoom a single axis or both.
- Hold the middle mouse button (or the wheel) and drag in any direction to pan.

Plotting - Copy and Paste





Plotting - Better Defaults





Plotting - Markers in Legend






Plotting - Upcoming


- 1. Markers: Allow references to scalar slots
- 2. Set Y-axis time range via RPL Function

Output Canvas

Output Canvas - Flow Line Legend



Output Canvas - Export to Video



RPL Enhancements


Read/Write Text Series Slots

- Read/write text series slots
- Conversion functions:
 - StringToTextSlotNumeric
 - GetTextSlotValueAsString
 - TextSlotNumericToString

	Big Res Data .Release Reason Text		×	^
10-26-2018 Fri	Irrigation Season	R	1	
10-27-2018 Sat	Irrigation Season	R	1	
10-28-2018 Sun	Irrigation Season	R	1	
10-29-2018 Mon	Irrigation Season	R	1	
10-30-2018 Tue	Irrigation Season	R	1	
10-31-2018 Wed	Start of Flood Control	R	1	
11-01-2018 Thu	In Flood Control	R	1	
11-02-2018 Fri	In Flood Control	R	1	
11-03-2018 Sat	In Flood Control	R	1	~


```
Big Res Data.Release Reason [] = IF (Start of Flood Season ()) THEN
StringToTextSlotNumeric ("Start of Flood Control")
ELSE IF (In Flood Season ()) THEN
StringToTextSlotNumeric ("In Flood Control")
ELSE
StringToTextSlotNumeric ("Irrigation Season")
END IF
```

New Alert and Notice Statements





New Statement Menu



New RPL Predefined Functions

- Get3DTableValsSkipNaN
- MemoryUsage
- OptDualPrice
- OptReducedCost
- GetTextSlotValueAsString

- GetSlotNameAndCol
- StringToTextSlotNumeric,
- TextSlotNumericToString
- RoundToFactor
- TableLookupDefaultTol